

# RELEASE NOTES

SMARTRAY DEVKIT 6.0.13.15 updated on June 21<sup>st</sup> 2024



## Recommended Firmware Version

3D Sensor Series	Firmware Version
ECCO 85+	6.1.1.7
ECCO 95+	6.1.1.7
ECCO X	6.1.2.16

## What's new?

### API

- Public multi ROI interface
- Samples (C, C++, C#, Python) are extended with multi ROI examples
- SR\_API\_GetSensorMinDimensions public function to get the minimum ROI width and height values
- Support of Linux 32bit/ 64bit, Linux ARM 32bit/ 64bit and Windows 64bit
- No further support of Windows 32bit

### SmartRay Demonstrator

Nothing

## Fixed issues

### API

- Fix in loading "Ready for Acquisition Status Signal" setting from parameter set file
- Fix in acquiring P (Profile) and Z (Z-Map) only mode
- Fix parameter list of SetPrefilterDefault in C# interface
- Fix of intensity outliers on ZIL data
- Fix of SmartXtract zero point indication

### SmartRay Demonstrator

none

## Known Issues

### API

- When using multiple exposure and the exposure times are not in order from shortest to longest, leads to delivery of unexpected blank data blocks.

### SmartRay Demonstrator

none

# Previous Release

# RELEASE NOTES

SMARTRAY DEVKIT 6.0.6.8 updated on Jan 29th 2024



## Recommended Firmware Version

3D Sensor Series	Firmware Version
ECCO 85+	5.5.2.2
ECCO 95+	5.5.0.5
ECCO X	6.1.0.11

## What's new?

Initial Release 6.0

### **API**

Initial version for ECCO X support

### **SmartRay Demonstrator**

Initial version

## Fixed issues

### API

none

### SmartRay Demonstrator

none



## Known Issues

### API

none

### SmartRay Demonstrator

none